

SOYBEAN* (PREPLANT ONLY)

	Amount of Spitfire per Acre	Minimum Waiting Interval Before Planting Soybeans	Directions
Preplant	1.0 to 1.25 pints	7 Days†	Apply before planting soybeans to control actively growing emerged broadleaf weeds. Following application, a minimum accumulation of 1/2" rainfall or overhead irrigation followed by the specified minimum waiting interval, is required before planting soybeans.
	1.25 to 2.0 pints	15 Days†	Apply before planting soybeans to control actively growing emerged broadleaf weeds. Following application, a minimum accumulation of 1" rainfall or overhead irrigation followed by the specified minimum waiting interval, is required before planting soybeans.
	2.0 to 2.5 pints	30 Days†	Apply before planting soybeans to control actively growing emerged broadleaf weeds. Following application, a minimum accumulation of 1" rainfall or overhead irrigation followed by the specified minimum waiting interval, is required before planting soybeans.
Soybean Restrictions:			
<ul style="list-style-type: none"> • For use only preplant to soybeans. • Do not apply more than 2.5 pints of this product per acre per growing season under these directions for preplant application to soybeans. • Only one application of this product may be made per growing season under these directions for preplant application to soybeans. • Do not apply this product prior to planting soybeans if you are not prepared to accept the results of soybean injury including possible loss of stand and yield. • Do not replant fields treated with this product in the same growing season with crops other than those labeled for 2,4-D and dicamba pre-plant use. • Do not mow or cultivate weeds prior to treating with this product as poor control may result. • Do not apply this product pre-plant to soybean in fields having a coarse-textured soil where the organic matter is less than 1%. • Livestock should be restricted from feeding/grazing of treated cover crops. Do not cut treated cover crops for hay or feed. • The minimum waiting intervals must be observed prior to planting soybean or crop injury may occur. • Do not make preplant applications of this product to soybean in geographic areas with average annual rainfall less than 25". 			
*Not currently registered for use in California.			
Notes:			
<ul style="list-style-type: none"> • Refer to Table 1 to determine use rates for specific targeted weed species, but do not exceed rate stated for soybeans preplant. • Use the higher listed rates for larger or difficult-to-control weeds. • For applications applied 60 or more days† before planting soybeans, follow the directions and precautions for Postharvest, Fallow, Crop Stubble listed in Section VII of the container label. • Best results will be obtained when product is mixed with additives or tank mixed with additional herbicides see ADDITIVES and TANK MIXING INFORMATION sections of label. 			
†Minimum waiting interval excludes days when ground is frozen.			